


Chapter 7

The Theory and Estimation of Production

*Managerial Economics: Economic
Tools for Today's Decision Makers, 4/e
By Paul Keat and Philip Young*




The Theory and Estimation of Production

- The Production Function
- Production in the Short Run
 - Total, Average, and Marginal Product
 - Law of Diminishing Returns
 - Stages of Production
 - Optimal Input Usage
- Production in the Long Run
 - Returns to Scale



The Production Function

- A **production function** defines the relationship between inputs and the maximum amount that can be produced within a given time period with a given technology.




The Production Function

- Mathematically, the production function can be expressed as

$$Q=f(X_1,X_2,\dots,X_k)$$

- Q is the level of output
- X_1,X_2,\dots,X_k are the levels of the inputs in the production process
- $f()$ represents the production technology




The Production Function

- For simplicity we will often consider a production function of two inputs:


$$Q=f(X, Y)$$

- Q is output
- X is Labor
- Y is Capital




The Production Function

- When discussing production, it is important to distinguish between two time frames.
- The **short-run production function** describes the maximum quantity of good or service that can be produced by a set of inputs, *assuming that at least one of the inputs is fixed at some level.*




The Production Function

- The **long-run production function** describes the maximum quantity of good or service that can be produced by a set of inputs, *assuming that the firm is free to adjust the level of all inputs.*




Production in the Short Run

- When discussing production in the short run, three definitions are important.
 - Total Product
 - Marginal Product
 - Average Product




Production in the Short Run

- Total product (TP) is another name for output in the short run. The total product function is the same as the short run production function.




Production in the Short Run

- The marginal product (MP) of a variable input is the change in output (or TP) resulting from a one unit change in the input.
- MP tells us how output changes as we change the level of the input by one unit.



Production in the Short Run

- The average product (AP) of an input is the total product divided by the level of the input.
- AP tells us, on average, how many units of output are produced per unit of input used.




Production in the Short Run

- Consider the two input production function $Q=f(X, Y)$ in which input X is variable and input Y is fixed at some level.
- The marginal product of input X is defined as

$$MP_X = \frac{\Delta Q}{\Delta X}$$

holding input Y constant.



Production in the Short Run

- The average product of input X is defined as

$$AP_X = \frac{Q}{X}$$

holding input Y constant.

Production in the Short Run

The table below represents a firm's production function, $Q=f(X,Y)$:

Units of Y Employed	Output Quantity (Q)							
8	37	60	83	96	107	117	127	128
7	42	64	78	90	101	110	119	120
6	37	52	64	73	82	90	97	104
5	31	47	58	67	75	82	89	95
4	24	39	52	60	67	73	79	85
3	17	29	41	52	58	64	69	73
2	8	18	29	39	47	52	56	52
1	4	8	14	20	27	24	21	17
	1	2	3	4	5	6	7	8
	Units of X Employed							

Production in the Short Run

In the short run, let $Y=2$. The row highlighted below represents the firm's short run production function.

Units of Y Employed	Output Quantity (Q)							
8	37	60	83	96	107	117	127	128
7	42	64	78	90	101	110	119	120
6	37	52	64	73	82	90	97	104
5	31	47	58	67	75	82	89	95
4	24	39	52	60	67	73	79	85
3	17	29	41	52	58	64	69	73
2	8	18	29	39	47	52	56	52
1	4	8	14	20	27	24	21	17
	1	2	3	4	5	6	7	8
	Units of X Employed							



Production in the Short Run

- Rewriting this row, we can create the following table and calculate values of marginal and average product.

Variable Input (X)	Total Product (Q or TP)
0	0
1	8
2	18
3	29
4	39
5	47
6	52
7	56
8	52

Calculation of Marginal Product

Variable Input (X)	Total Product (Q or TP)	Marginal Product (MP)
0	0	$\frac{\Delta Q}{\Delta X} = \frac{8}{1} = 8$
1	8	
2	18	
3	29	
4	39	
5	47	
6	52	
7	56	
8	52	

Calculation of Marginal Product

Variable Input (X)	Total Product (Q or TP)	Marginal Product (MP)
0	0	8
1	8	10
2	18	11
3	29	10
4	39	8
5	47	$\frac{\Delta Q}{\Delta X} = \frac{5}{1} = 5$
6	52	
7	56	4
8	52	-4

Calculation of Average Product

Variable Input (X)	Total Product (Q or TP)	Average Product (AP)
0	0	
1	8	$\frac{Q}{X} = \frac{8}{1} = 8$
2	18	
3	29	
4	39	
5	47	
6	52	
7	56	
8	52	




Calculation of Average Product

Variable Input (X)	Total Product (Q or TP)	Average Product (AP)
0	0	---
1	8	8
2	18	9
3	29	9.67
4	39	9.75
5	47	9.4
6	52	8.67
7	56	8
8	52	6.5


Production in the Short Run

- The figures illustrate TP, MP, and AP graphically.




Production in the Short Run


- If MP is positive then TP is increasing.
- If MP is negative then TP is decreasing.
- TP reaches a maximum when $MP=0$



Production in the Short Run

- If $MP > AP$ then AP is rising.
- If $MP < AP$ then AP is falling.
- $MP = AP$ when AP is maximized.






The Law of Diminishing Returns

- Definition
 - As additional units of a variable input are combined with a fixed input, at some point the additional output (i.e., marginal product) starts to diminish.

Diminishing Returns

Variable Input (X)	Total Product (Q or TP)	Marginal Product (MP)
0	0	8
1	8	10
2	18	11
3	29	10
4	39	8
5	47	5
6	52	4
7	56	4
8	52	-4

Diminishing
Returns
Begins
Here





The Law of Diminishing Returns

- Reasons

Increasing Returns

Teamwork and Specialization







The Three Stages of Production

- Stage I
 - From zero units of the variable input to where AP is maximized
- Stage II
 - From the maximum AP to where $MP=0$
- Stage III
 - From where $MP=0$ on


The Three Stages of Production





The Three Stages of Production

- In the short run, rational firms should only be operating in Stage II.
- Why Stage II?
 - Why not Stage III?
 - Firm uses more variable inputs to produce less output!
 - Why not Stage I?
 - Underutilizing fixed capacity.
 - Can increase output per unit by increasing the amount of the variable input.




Optimal Level of Variable Input Usage

- Consider the following short run production process.

Labor Unit (X)	Total Product (Q or TP)	Average Product (AP)	Marginal Product (MP)
0	0		
1	10,000	10,000	10,000
2	25,000	12,500	15,000
3	45,000	15,000	20,000
4	60,000	15,000	15,000
5	70,000	14,000	10,000
6	75,000	12,500	5,000
7	78,000	11,143	3,000
8	80,000	10,000	2,000


Where
is
Stage
II?



Optimal Level of Variable Input Usage


Labor Unit (X)	Total Product (Q or TP)	Average Product (AP)	Marginal Product (MP)
0	0		
1	10,000	10,000	10,000
2	25,000	12,500	15,000
3	45,000	15,000	20,000
4	60,000	15,000	15,000
5	70,000	14,000	10,000
6	75,000	12,500	5,000
7	78,000	11,143	3,000
8	80,000	10,000	2,000

Stage II




Optimal Level of Variable Input Usage

- What level of input usage within Stage II is best for the firm?
- The answer depends upon how many units of output the firm can sell, the price of the product, and the monetary costs of employing the variable input.



Optimal Level of Variable Input Usage

- In order to determine the optimal input usage we assume that the firm operates in a perfectly competitive market for its input and its output.
 - Product price, $P = \$2$
 - Variable input price, $w = \$10,000$



Optimal Level of Variable Input Usage

- Define the following
 - Total Revenue Product (TRP) = $Q \cdot P$
 - Marginal Revenue Product (MRP) =

$$\frac{\Delta TRP}{\Delta X} = \frac{\Delta(Q \cdot P)}{\Delta X} = \frac{P \cdot \Delta Q}{\Delta X} = P \cdot MP$$

- Total Labor Cost (TLC) = $w \cdot X$

- Marginal Labor Cost (MLC) = $\frac{\Delta TLC}{\Delta X} = w$

Optimal Level of Variable Input Usage


Labor Unit (X)	Total Product (Q or TP)	Average Product (AP)	Marginal Product (MP)	Total Revenue Product (TRP)	Marginal Revenue Product (MRP)	Total Labor Cost (TLC)	Marginal Labor Cost (MLC)	TRP-TLC	MRP-MLC
0	0			0		0		0	
1	10,000	10,000	10,000	20,000	20,000	10,000	10,000	10,000	10,000
2	25,000	12,500	15,000	50,000	30,000	20,000	10,000	30,000	20,000
3	45,000	15,000	20,000	90,000	40,000	30,000	10,000	60,000	30,000
4	60,000	15,000	15,000	120,000	30,000	40,000	10,000	80,000	20,000
5	70,000	14,000	10,000	140,000	20,000	50,000	10,000	90,000	10,000
6	75,000	12,500	5,000	150,000	10,000	60,000	10,000	90,000	0
7	78,000	11,143	3,000	156,000	6,000	70,000	10,000	86,000	-4,000
8	80,000	10,000	2,000	160,000	4,000	80,000	10,000	80,000	-6,000

Optimal Level of Variable Input Usage

Labor Unit (X)	Total Product (Q or TP)	Average Product (AP)	Marginal Product (MP)	Total Revenue Product (TRP)	Marginal Revenue Product (MRP)	Total Labor Cost (TLC)	Marginal Labor Cost (MLC)	TRP- TLC	MRP- MLC
0	0			0		0		0	
1	10,000	10,000	10,000	20,000	20,000	10,000	10,000	10,000	10,000
2	25,000	12,500	15,000	50,000	30,000	20,000	10,000	30,000	20,000
3	45,000	15,000	20,000	90,000	40,000	30,000	10,000	60,000	30,000
4	60,000	15,000	15,000	120,000	30,000	40,000	10,000	80,000	20,000
5	70,000	14,000	10,000	140,000	20,000	50,000	10,000	90,000	10,000
6	75,000	12,500	5,000	150,000	10,000	60,000	10,000	90,000	0
7	78,000	11,143	3,000	156,000	6,000	70,000	10,000	86,000	-4,000
8	80,000	10,000	2,000	160,000	4,000	80,000	10,000	80,000	-6,000


Stage II





Optimal Level of Variable Input Usage


- A profit-maximizing firm operating in perfectly competitive output and input markets will be using the optimal amount of an input at the point at which the monetary value of the input's marginal product is equal to the additional cost of using that input.
- Where $MRP=MLC$.



Optimal Level of Variable Input Usage

- When the firm employs multiple variable inputs, the firm should choose the level of the inputs which equates the marginal product per dollar across each of the inputs. Mathematically,

$$\frac{MP_1}{w_1} = \frac{MP_2}{w_2} = \dots = \frac{MP_k}{w_k}$$




Production in the Long Run

- In the long run, all inputs are variable.
- The long run production process is described by the concept of **returns to scale**.
- Returns to scale describes what happens to total output as all of the inputs are changed by the same proportion.



Production in the Long Run

- If all inputs into the production process are doubled, three things can happen:
 - output can more than double
 - increasing returns to scale (IRTS)
 - output can exactly double
 - constant returns to scale (CRTS)
 - output can less than double
 - decreasing returns to scale (DRTS)




Production in the Long Run

One way to measure returns to scale is to use a coefficient of output elasticity:

$$E_Q = \frac{\text{Percentage change in } Q}{\text{Percentage change in all inputs}}$$

- If $E > 1$ then IRTS
- If $E = 1$ then CRTS
- If $E < 1$ then DRTS



Production in the Long Run




- Returns to scale can also be described using the following equation

$$hQ=f(kX,kY)$$

- If $h>k$ then IRTS
- If $h=k$ then CRTS
- If $h<k$ then DRTS

Production in the Long Run

- Graphically, the returns to scale concept can be illustrated using the following graphs.



Production in the Long Run

- Economists hypothesize that a firm's long run production function may exhibit at first increasing returns, then constant returns, and finally decreasing returns to scale.

